



DH2i DxEnterprise 20.0 Software: MSSQL Availability Groups with DxCLI Quick Start Guide

DH2i Company

Support: +1 (800) 380-5405 ext. 2

<https://dh2i.com/support/>

eFax: +1 970-295-4505

Email: support@dh2i.com

<https://www.dh2i.com>

MSSQL Availability Groups with DxCLI

This quick start guide describes how to set up and configure Microsoft SQL Server availability groups on DxEnterprise using DxCLI. Using this guide, the user will add a Vhost, create an availability group, add databases, and add a SQL listener.

Prerequisites

The following configuration must be met before continuing:

- Two nodes (virtual or physical) with DxEnterprise installed and joined together into a cluster are required. For information about installing and configuring DxEnterprise, see the [Ubuntu](#), [RHEL/CentOS](#), or [Windows](#) installation quick start guides. For cloud platforms with DxEnterprise pre-installed, view the [Azure](#) or [AWS](#) quick start guides.
- Microsoft SQL Server (MSSQL) 2017 or later must be installed on each server (node). Reference [Microsoft documentation](#) for instructions on installing SQL Server.
- A valid DxEnterprise license with availability group management features enabled. If tunnels will be used for availability group connections, tunneling features must also be enabled.

NOTE: Visit the [Client Portal](#) to view license status. To enable availability group management and/or tunneling features, please contact your DH2i account representative. To obtain a license, contact sales@dh2i.com.

Create Availability Group on the First Node

1. Connect to the first server (node) via SSH or RDP.
2. Open Command Prompt or Terminal session with elevated privileges.
 - Windows only: change directory to C:\Program Files\DH2i\bin
3. DxEnterprise uses Virtual Hosts (Vhosts) to provide failover support and high availability. A Vhost virtualizes the network name and IP address associated to a particular SQL instance, and instead of using the network name and IP address of a physical server, a Vhost is created and assigned a unique name/IP-address pair. Clients access the databases associated with an instance via the Vhost name or IP address; they do not need to know which node is running the SQL instance. To add a Vhost, use the `dxcli cluster-add-vhost` command.

Syntax

```
dxcli cluster-add-vhost <vhost> <vips> <nodes> [autofailback]
[priority[1-5]] [ilb_ports]
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True
vips	The virtual IP(s) for the Vhost (comma-separated list for multiples). The use of a loopback address (127.0.0.1) is supported, but must be preceded by an asterisk (*).	True
nodes	The nodes(s) to add to the Vhost (comma-separated list for multiples).	True

autofailback	Set autofailback option, or leave blank if autofailback is not desired.	False
priority	The priority order of failover between Vhosts (1 is the highest and 5 is the lowest).	False
ilb_ports	Port to use for internal load balancer probing (comma-separated list for multiples).	False

Example

```
dxcli cluster-add-vhost vhost1 *127.0.0.1 dxemssql1
```

- Use the `dxcli encrypt-text` command to encrypt the SQL Server sysadmin password. The encrypted password will be used in the next step for the creation of the availability group.

Syntax

```
dxcli encrypt-text <value>
```

Parameters

Name	Description	Required
value	The text to be encrypted.	True

Example

```
dxcli encrypt-text p@ssw0rd
```

- To add an availability group to the Vhost, use the `dxcli add-ags` command. The SQL Server sysadmin password must be encrypted using the command in the previous step.

NOTE: *If tunneling is not enabled for your DxEnterprise license, omit the tunnel port parameter. Pay-as-you-go licenses on Azure and AWS have NAT and tunneling enabled. To view license status and features, visit the [DH2i Client Portal](#).*

Syntax

```
dxcli add-ags <vhost> <ags_name>
<node_name|instance_name|sql_login|sql_pass|mirror_port|availability
_mode|[tunnel_port]>
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True
ags_name	The name of the availability group.	True
node_name	The name of the node.	True
instance_name	The name of the instance.	True
sql_login	A SQL server sysadmin user. If using Windows authentication, the credential must be supplied in UPN format (e.g. user@domain.com).	True
sql_pass	The password for the SQL Server sysadmin user (encrypted using “dxcli encrypt-text”).	True

mirror_port	The mirroring port to use for the availability group (default is 5022).	True
availability_mode	Synchronous_commit, asynchronous_commit or configuration only.	True
tunnel_port	The port to be used for the tunnel connections (for cross availability zone, cross-region). This port should be unique per node.	False

Example

```
dxcli add-ags vhost1 ags1
"dxemssql1|mssqlserver|sa|6pnFaDrRS+W/F+dkRuPKAA==|5022|synchronous_
commit|25022"
```

Join the Second Node and Add to Availability Group

1. Add the second node to the existing availability group and Vhost using the `dxcli add-ags-node` command. The SQL Server sysadmin password must be encrypted using the `dxcli encrypt-text` command.

NOTE: *If tunneling is not enabled for your DxEnterprise license, omit the tunnel port parameter.*

Syntax

```
dxcli add-ags-node <vhost> <ags_name>
<node_name|instance_name|sql_login|sql_pass|mirror_port|availability_
_mode|[tunnel_port]>
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True
ags_name	The name of the availability group.	True
node_name	The name of the node.	True
instance_name	The name of the instance.	True
sql_login	A SQL server sysadmin user. If using Windows authentication, the credential must be supplied in UPN format (e.g. user@domain.com)	True
sql_pass	The password for the SQL Server sysadmin user (encrypted using “dxcli encrypt-text”)	True
mirror_port	The mirroring port to use for the availability group (default is 5022).	True
availability_mode	Synchronous_commit, asynchronous_commit or configuration only.	True
tunnel_port	The port to be used for the tunnel connections (for cross availability zone, cross-region). This port should be unique per node.	False

Example

```
dxcli add-ags-node vhost1 ags1
"dxemssql2|mssqlserver|sa|6pnFaDrRS+W/F+dkRuPKAA==|5022|synchronous_
commit|35022"
```

2. Add databases to the availability group using the `dxcli add-ags-databases` command. The databases will be automatically replicated to the other node in the availability group.

Syntax

```
dxcli add-ags-databases <vhost> <ags_name> <db_name>
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True
ags_name	The name of the availability group.	True
db_name	The name of the SQL Server database (comma-separated list for multiples).	True

Example

```
dxcli add-ags-databases vhost1 ags1 db1,db2,db3
```

3. Verify the details of the availability group using the `dxcli get-ags-detail` command.

Syntax

```
dxcli get-ags-detail <vhost> <ags_name>
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True
ags_name	The name of the availability group.	True

Example

```
dxcli get-ags-detail vhost1 ags1
```

4. Optional: Add a listener using the `add-ags-listener` command. SQL Server listeners allow a client to connect to a replica of the availability group without having to know the SQL Server instance name. An availability group listener consists of a DNS listener name (Vhost name), listener port designation, and one or more IP addresses (Vhost IP address).

NOTE: *When the cluster type is set to "external" or "none", availability group listeners only function with SQL Server 2019 or later. To connect to an availability group listener via Kerberos authentication, please reference [Microsoft documentation](#).*

Syntax

```
dxcli add-ags-listener <vhost> <ags_name> <port>
```

Parameters

Name	Description	Required
vhost	The name of the Vhost.	True

ags_name	The name of the availability group.	True
port	The port number for the listener.	True

Example

```
dxcli add-ags-listener vhost1 ags1 42002
```

References

- [DH2i Support Portal](#)
- [DxEnterprise v20.0 Documentation](#)
- [DxEnterprise v20.0 Admin Guide](#)
- [DxEnterprise v20.0 DxCli Guide](#)
- [Microsoft - Connect to an Always On availability group listener: SPNs](#)
- [Microsoft - Install SQL Server](#)