



DH2i DxEnterprise 20.0 Software: DxConfiguration Manager Administration Guide

DH2i Company

Support: +1 (800) 380-5405 ext 2

support.dh2i.com


eFax: +1 970-295-4505

support@dh2i.com

www.dh2i.com

DxConfiguration Manager Overview


DxConfiguration Manager is DH2i's client software that is used to configure first time installs on Windows servers running DxEnterprise or DxOdyssey. Once the configuration has been completed administrators will be able to access DxEnterprise or DxOdyssey for purposes of administration and management duties.



Server Status

Shows current state of the server with the option to stop or start DxEnterprise or DxOdyssey as needed.

Activate License




Automatic over the internet

Select this if the server has internet access and can activate the license with DH2i activation servers. Enter the license code and check the Accept End User License Agreement (EULA) box.

Manual activation

Select this option if the server does not have internet access. The license request is generated for the given license code and must be activated through DH2i Clients portal or from a workstation with internet access. The DH2i activation website is at <https://clients.dh2i.com>. Copy and paste the result from Clients Activation portal in the License box, check the EULA box and select Activate.




The screenshot shows a window titled "License Management" with standard Windows window controls (minimize, maximize, close). The window contains the following elements:

- Two radio buttons for activation methods: "Automatic over the internet" (unselected) and "Manual activation" (selected).
- A text input field labeled "License code:" containing the text "AAAA-BBBB-CCCC-DDDD".
- A large empty text area labeled "License request:" with a vertical scrollbar on the right.
- A "License:" label followed by a "Copy" button and a large empty text area with a vertical scrollbar on the right.
- At the bottom, an "Accept EULA" checkbox (unchecked) with a "View EULA" link below it, and two buttons: "Activate" and "Close".

Set Passkey


A pass key is required to log in to the cluster or gateway group for administration. The pass key is case-sensitive and can be any combination of alpha-numeric characters, punctuation, or symbols. If the user has not configured a pass key or has forgotten the pass key, the user will be unable to log in remotely or log in using unprivileged accounts.



The screenshot shows a dialog box titled "Passkey Management". It features a text input field labeled "Passkey:" and two buttons at the bottom: "Submit" and "Close".

Join Membership

The Join Membership option allows administrative re-assignment of the local server to another existing DxEnterprise cluster or DxOdyssey gateway group.



The screenshot shows a dialog box titled "Membership Management". It contains a checkbox labeled "Join via NAT Match Agent. Only select this option if you have a valid One-Time PassKey". Below this, there are two text input fields: "Target Member" and "Pass Key". At the bottom, there are two buttons: "OK" and "Close".

NatMatchAgent Checkbox

If the NatMatchAgent checkbox is selected, the default value of the target member is match.DH2i.com. This allows server to join the quorum from remote locations using the DH2i matchmaking service.

Target Member

Enter the hostname or IP address of a server from an existing DxEnterprise cluster or DxOdyssey gateway group.

Pass Key

Enter the passkey or OTPK previously set for the existing cluster or gateway group.

OK


Click to process the request.

Close



Click to cancel and exit without saving change(s).

Manage OTPK

Set a One-Time PassKey (OTPK) for the cluster or gateway group that can be used by other servers to join using DH2i matchmaking service.



Select New and a window will appear that allows setting a time and date for expiration of the OTPK. The default is one hour.



The OTPK is now set for use to join membership via DH2i matchmaking service.

References

- [DH2i Product Documentation](#)
- [DH2i Support Portal](#)