



DH2i DxOdyssey 20.0 Software: Installation Reference Guide for Ubuntu

DH2i Company

Support: +1 (800) 380-5405 ext. 2

<https://dh2i.com/support/>

eFax: +1 970-295-4505

Email: support@dh2i.com

<https://www.dh2i.com>

Installation Reference for Ubuntu

This guide is command reference for installing DxOdyssey and its dependencies on Ubuntu. For a more detailed installation guide, view the Installation Quick Start Guide for Ubuntu.

Install Dependencies and Applications

Install updates

- `sudo apt-get update`
- `sudo apt-get dist-upgrade`

Set host resolution for all nodes and Vhosts

- `sudo nano /etc/hosts`

Ensure hostname is set and unique

- `hostname`
- `sudo hostnamectl set-hostname <name>`

NOTE: A system restart is required to apply changes.

Download Microsoft package signing key (Ubuntu 16.04)

- `wget https://packages.microsoft.com/config/ubuntu/16.04/packages-microsoft-prod.deb -O packages-microsoft-prod.deb`

Download Microsoft package signing key (Ubuntu 18.04)

- `wget https://packages.microsoft.com/config/ubuntu/18.04/packages-microsoft-prod.deb -O packages-microsoft-prod.deb`

Download Microsoft package signing key (Ubuntu 20.04)

- `wget https://packages.microsoft.com/config/ubuntu/20.04/packages-microsoft-prod.deb -O packages-microsoft-prod.deb`

Add Microsoft package repository and Install .NET Core

- `sudo dpkg -i packages-microsoft-prod.deb`
- `sudo apt-get update`
- `sudo apt-get install apt-transport-https`
- `sudo apt-get update`
- `sudo apt-get install dotnet-runtime-3.1`

Install remaining dependencies

- `sudo apt-get install zip`

Download DH2i package signing key

- `wget -qO- https://repos.dh2i.com/public.gpg | sudo gpg --dearmor -o /etc/apt/trusted.gpg.d/dh2i.gpg`

Register the DH2i Ubuntu repository

- `sudo sh -c 'echo deb [arch=amd64] https://repos.dh2i.com/ bionic retail >/etc/apt/sources.list.d/dh2i.list'`

NOTE: The architecture parameter [arch=amd64] can be changed to arm64 or armhf to install DxOdyssey on those platforms.

Update the package list and install DxOdyssey

- `sudo apt-get update`
- `sudo apt-get install -y dxodyssey`

Configure DxOdyssey

Activate server license

- `sudo dxcli activate-server AAAA-BBBB-CCCC-DDDD`

Set gateway group passkey (first gateway installation)

- `sudo dxcli gateway-group-set-secret`

Set One-Time PassKey (first gateway installation)

- `sudo dxcli set-otpk`

Join existing gateway group

- `sudo dxcli join-gateway-group`

References

- [DH2i Product Documentation](#)
- [DxOdyssey v20.0 DxCli Guide](#)
- [DxOdyssey v20.0 Admin Guide](#)
- [Microsoft – Install .NET Core SDK or NET Core Runtime on Ubuntu](#)